

DIGIMERGE

Service Bulletin

Version 1.16.F

April 4, 2006

RELEASE DATE:

April 4, 2006

PRODUCT:

DHT304/404

PURPOSE:

To provide installation instructions for the Version 1.16.F Firmware update.

Upgrade features:

- Improves the time search feature on older versions of the DHT firmware
- Improves the USB backup on DHT firmware v1.16.E.

PROCEDURE:

Please read the entire document before proceeding.

PREPARE THE DOWNLOADED FILE:

1. Download the firmware update from the Digimerge website.
2. Copy the firmware update file **dht_dvr4.bin** to a USB flash drive. This file **must** be copied to the root of the USB drive.

UPGRADING THE FIRMWARE:

1. Insert the USB key into the DHT unit. Press the **MENU** button on the unit, and select the **FIRMWARE UPGRADE** option. Select **YES** to upgrade the firmware.

(Do not touch the unit until the upgrade is complete)

2. When the upgrade is complete, the DVR will return to the **FIRMWARE UPGRADE** menu. Select **NO** to continue.
3. Exit the menu and power down the unit for 2 minutes.
4. Power up the DVR. Confirm the firmware is Version 1.16.F.

TROUBLESHOOTING:

If the firmware does not apply correctly on the DVR unit, proceed with the following:

Reset the unit to Factory Defaults:

1. Press the **MENU** button on the unit, and select the **SYSTEM (I)** option.
2. Set the **DEFAULT SET** option to **[Y]**.
3. Exit the menu to reset the DVR unit.
4. Repeat the **FIRMWARE UPGRADE** process.