

DIGIMERGE

Firmware Upgrade

Version 1.16A

Nov 19,2005

RELEASE DATE : Jan 09, 2006

PRODUCT : DHT304 / 404

PURPOSE: To provide information about of how to install the new firmware .

PROCEDURE: If the system software of the DHT304/ 404 DVR needs to be upgraded, please take the following steps to safely update it. Before you proceed read the entire document.

1. PREPARE THE DOWNLOADED FILE.

a. If you downloaded the file from the website make sure to prepare and copy the file :

- **Firmware for dht_dvr4.zip** for DHT304/404

b. **Unzip** the file **using** the WINZIP program into a folder on your PC and make sure the unzipped file in a **.BIN** format. Copy the **BIN** file **dht_dvr4.bin** (**not in a folder**) to a USB flash drive



USB flash drive

3. UPGRADING THE FIRMWARE

1. Copy the **bin** file to a USB flash drive (to the root of the drive ie: not inside a folder)
2. Insert the USB key into the DHT unit and go to the menu →**Firmware Upgrade**, and upgrade the firmware.
3. When the upgrade is complete the DVR will go back to the Firmware Upgrade menu. (Do not touch the unit until the upgrade is complete.)
4. Check and note the new firmware version on the unit
5. Exit the menu and power down the unit for 2 minutes.
6. After upgrading, please reset the unit to factory defaults. (System1→Default Set).

Digimerge Technologies Inc.

300 Alden Road • Markham • Ontario • Canada • L3R4C1
tel: (905)946-8477 • fax: (905)947-0138